



Message Implementation Guideline

DHL FREIGHT (SWEDEN) STATUS MESSAGE

based on

IFTSTA

International multimodal status report message

UN D.94B S3

Version:	2.1
Issue date:	2021-10-15
Author:	CHRISTER SJÖLUND



Contents

Contents

Release notes version 2.1 3

Message structure overview 3

Structure / Table of contents 4

Segments..... 5

Example message27

Version history28

Release notes**Release notes version 2.1**

Sg	Segment	DE	Modification/Comment
4	RFF	1153	Added qualifier ACE for Related shipment number.
5	DTM	2005	Segment added. Date/time qualifier
		2380	Date/time period
		2379	Date/time period qualifier

Structure / Table of Contents

Counter	No	Tag	St	MaxOcc	Level	Content	
0000	1	UNA	C	1	0	SERVICE STRING ADVICE	UNA
0000	2	UNB	M	1	0	INTERCHANGE HEADER	UNB
0010	3	UNH	M	1	0	Message header	UNH
0020	4	BGM	M	1	0	Beginning of message	BGM
0030	5	DTM	C	1	1	Date/time/period	DTM
0050		SG1	M	1	1	NAD	SG1
0060	6	NAD	M	1	1	Name and address	NAD
0140		SG3	C	999	1	CNI-SG4	SG3
0150	7	CNI	M	1	1	Consignment information	CNI
0180		SG4	M	99	2	STS-RFF-DTM-FTX-NAD-LOC-SG5-SG8	SG4
0190	8	STS	M	1	2	Status	STS
0200	9	RFF	C	9	3	Reference	RFF
0210	10	DTM	C	1	3	Date/time/period	DTM
0220	11	FTX	C	1	3	Free text	FTX
0230	12	NAD	C	9	3	Name and address	NAD
0240	13	LOC	C	1	3	Place/location identification	LOC
0260		SG5	C	1	3	TDT-LOC-DTM	SG5
0270	14	TDT	M	1	3	Details of transport	TDT
0290	15	LOC	C	2	4	Place/location identification	LOC
0300	16	DTM	C	9	4	Date/time/period	DTM
0390		SG8	C	99	3	GID-PCI-SG9-SG10	SG8
0400	17	GID	M	1	3	Goods item details	GID
0420	18	PCI	C	99	4	Package identification	PCI
0430		SG9	C	99	4	MEA	SG9
0440	19	MEA	M	1	4	Measurements	MEA
0460		SG10	C	99	4	DIM	SG10
0470	20	DIM	M	1	4	Dimensions	DIM
0490	21	UNT	M	1	0	Message trailer	UNT
0000	22	UNZ	M	1	0	INTERCHANGE TRAILER	UNZ

Counter = Counter of segment/group within the standard
 No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Segments

Counter	No	Tag	St	MaxOcc	Level	Name	UNA
---------	----	-----	----	--------	-------	------	-----

0000 1 **UNA** C 1 0 **SERVICE STRING ADVICE**

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
UNA				
UNA1	Component data element separator	M an1	M an1	:
UNA2	Data element separator	M an1	M an1	+
UNA3	Decimal notation	M an1	M an1	.
UNA4	Release indicator	M an1	M an1	?
UNA5	Reserved for future use	M an1	M an1	
UNA6	Segment terminator	M an1	M an1	'

Remark:

Example:

UNA: + . ? '

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	UNB
---------	----	-----	----	--------	-------	------	-----

0000 2 **UNB** M 1 0 INTERCHANGE HEADER

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
UNB				
S001	SYNTAX IDENTIFIER	M	M	
0001	Syntax identifier	M a4	M a4	UNOC UN/ECE level C 3 Syntax version number 3
0002	Syntax version number	M n1	M n1	
S002	INTERCHANGE SENDER	M	M	
0004	Sender identification	M an..35	M an..35	
0007	Partner identification code qualifier	C an..4	C an..4	14 EAN (European Article Numbering Association) 30 ISO 6523: Organization identification
S003	INTERCHANGE RECIPIENT	M	M	
0010	Recipient identification	M an..35	M an..35	
0007	Partner identification code qualifier	C an..4	C an..4	14 EAN (European Article Numbering Association) 30 ISO 6523: Organization identification
S004	DATE/TIME OF PREPARATION	M	M	
0017	Date of preparation	M n6	M n6	
0019	Time of preparation	M n4	M n4	
0020	Interchange control reference	M an..14	M an..14	
S005	RECIPIENT'S REFERENCE	C	N	
	PASSWORD			
0022	Recipient's reference/password	M an..14	N	Not used
0026	Application reference	C an..14	C an..14	Not used for DHL Freight International

Remark:**Example:**

UNB+UNOC:3+7330924000002:14+7381000065002:14+120614:0918+123++IFTSTA'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	UNH
0010	3	UNH	M	1	0	Message header	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
UNH				
0062	Message reference number	M an..14	M an..14	
S009	MESSAGE IDENTIFIER	M	M	
0065	Message type identifier	M an..6	M an..6	IFTSTA International multimodal status report message
0052	Message type version number	M an..3	M an..3	D Draft directory
0054	Message type release number	M an..3	M an..3	94B Version 94B
0051	Controlling agency	M an..2	M an..2	UN UN/ECE/TRADE/WP.4, United Nations Standard Messages (UNSM)
0057	Association assigned code	C an..6	C an..6	SE0016 DHL Freight Domestic DP1.2 DHL Freight International

Remark:**Example:**

UNH+456+IFTSTA:D:94B:UN:SE0016'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	BGM
0020	4	BGM	M	1	0	Beginning of message	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
BGM				
C002	DOCUMENT/MESSAGE NAME	C	C	
1001	Document/message name, coded	C an..3	C an..3	I77 Item/Consignment status 77 Consignment status
1004	Document/message number	C an..35	C an..35	Not used for DHL Freight SE Domestic
1225	Message function, coded	C an..3	C an..3	9 Original

Remark:**Example:**

BGM+I77+123456+9'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	DTM
0030	5	DTM	C	1	1	Date/time/period	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
DTM				
C507	DATE/TIME/PERIOD	M	M	
2005	Date/time/period qualifier	M an..3	M an..3	137 Document/message date/time
2380	Date/time/period	C an..35	C an..35	
2379	Date/time/period format qualifier	C an..3	C an..3	102 CCYYMMDD 203 CCYYMMDDHHMM

Remark:**Example:**

DTM+137:20211007:102'

DTM+137:202110071245:203'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG1	NAD
0050		SG1	M	1	1	NAD		
0060	6	NAD	M	1	1	Name and address		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
NAD				
3035	Party qualifier	M an..3	M an..3	MS Document/message issuer/sender
C082	PARTY IDENTIFICATION DETAILS	C	N	
3039	Party id. identification	M an..35	N	Not used
C058	NAME AND ADDRESS	C	N	
3124	Name and address line	M an..35	N	Not used
C080	PARTY NAME	C	C	
3036	Party name	M an..35	M an..35	DHL Freight Sweden

Remark:**Example:**

NAD+MS+++DHL Freight Sweden'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG3	CNI
0140		SG3	C	999	1	CNI-SG4		
0150	7	CNI	M	1	1	Consignment information		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
CNI				
1490	Consolidation item number	C n..4	C n..4	
C503	DOCUMENT/MESSAGE DETAILS	C	C	
1004	Document/message number	C an..35	C an..35	DHL Freight Domestic: DHL shipment number DHL Freight International: DHL Order code

Remark:**Example:**

CNI+1+8005282440'

CNI+1+HAD-EC-9545754'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG4	STS
0180		SG4	M	99	2	STS-RFF-DTM-FTX-NAD-LOC-SG5-SG8		
0190	8	STS	M	1	2	Status		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
STS				
C601	STATUS TYPE	C	C	
9015	Status type, coded	M an..3	M an..3	1 Transport
C555	STATUS EVENT	C	C	
9011	Status event, coded	M an..3	M an..3	See separate code list
C556	STATUS REASON	C	C	
9013	Status reason, coded	M an..3	M an..3	See separate code list

Remark:**Example:**

STS+1+24+501'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG4	RFF
0180		SG4	M	99	2	STS-RFF-DTM-FTX-NAD-LOC-SG5-SG8		
0200	9	RFF	C	9	3	Reference		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
RFF				
C506	REFERENCE	M	M	
1153	Reference qualifier	M an..3	M an..3	AAS Transport document number CU Consignor reference AAO Consignee reference ACE Related shipment number Other references that are used in shipment information are also sent (maximum 9 repetitions).
1154	Reference number	C an..35	C an..35	

Remark:**Example:**

RFF+CU:16547832'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG4	DTM
0180		SG4	M	99	2	STS-RFF-DTM-FTX-NAD-LOC-SG5-SG8		
0210	10	DTM	C	1	3	Date/time/period		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
DTM				
C507	DATE/TIME/PERIOD	M	M	
2005	Date/time/period qualifier	M an..3	M an..3	7 Effective date/time
2380	Date/time/period	C an..35	C an..35	
2379	Date/time/period format qualifier	C an..3	C an..3	203 CCYYMMDDHHMM

Remark:**Example:**

DTM+7:202110071232:203'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG4	FTX
0180		SG4	M	99	2	STS-RFF-DTM-FTX-NAD-LOC-SG5-SG8		
0220	11	FTX	C	1	3	Free text		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
FTX				
4451	Text subject qualifier	M an..3	M an..3	ACB Additional information AAI Remark PRD Product information
4453	Text function, coded	C an..3	N	Not used
C107	TEXT REFERENCE	C	C	
4441	Free text, coded	M an..3	M an..3	Used with qualifier PRD: Product code
C108	TEXT LITERAL	C	C	
4440	Free text	M an..70	M an..70	Used with qualifier ACB: Status description Used with qualifier AAI: Remark Used with qualifier PRD: Product name

Remark:**Example:**

FTX+ACB+++Out for delivery'
 FTX+AAI+++Agreed delivery date 22.10.2021.'
 FTX+PRD++102+DHL PAKET'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG4	NAD
0180		SG4	M	99	2	STS-RFF-DTM-FTX-NAD-LOC-SG5-SG8		
0230	12	NAD	C	9	3	Name and address		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
NAD				
3035	Party qualifier	M an..3	M an..3	AP Accepting party FP Freight/charges payer CZ Consignor For DHL Freight International import shipments CZ equals the Consignee, i.e. the Swedish customer.
C082	PARTY IDENTIFICATION DETAILS	C	C	
3039	Party id. identification	M an..35	M an..35	Used with qualifier CZ: Consignor DHL account number
C058	NAME AND ADDRESS	C	N	
3124	Name and address line	M an..35	N	Not used
C080	PARTY NAME	C	C	
3036	Party name	M an..35	M an..35	Used with qualifier AP: Accepting party (IOD name)

Remark:**Example:**

NAD+AP+++Erika Svensson'
 NAD+CZ+405555'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG4	LOC
0180		SG4	M	99	2	STS-RFF-DTM-FTX-NAD-LOC-SG5-SG8		
0240	13	LOC	C	1	3	Place/location identification		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
LOC				
3227	Place/location qualifier	M an..3	M an..3	14 Event location
C517	LOCATION IDENTIFICATION	C	C	
3225	Place/location identification	C an..25	C an..25	For DHL Freight Domestic: DHL Terminal code For DHL Freight International: DHL Terminal name
1131	Code list qualifier	C an..3	N	Not used
3055	Code list responsible agency, coded	C an..3	N	Not used
3224	Place/location	C an..17	C an..17	Event location city name

Remark:**Example:**

LOC+14+3710::Växjö'

LOC+14+Hamburg::Hamburg'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG5	TDT
0260		SG5	C	1	3	TDT-LOC-DTM		
0270	14	TDT	M	1	3	Details of transport		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
TDT				
8051	Transport stage qualifier	M an..3	M an..3	20 Main-carriage transport

Remark:**Example:**

TDT+20 '

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG5	LOC
0260		SG5	C	1	3	TDT-LOC-DTM		
0290	15	LOC	C	2	4	Place/location identification		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
LOC				
3227	Place/location qualifier	M an..3	M an..3	5 Place of departure 8 Place of destination
C517	LOCATION IDENTIFICATION	C	C	
3225	Place/location identification	C an..25	C an..25	Postal code (including country code) Not used for DHL Freight Domestic
1131	Code list qualifier	C an..3	N	Not used
3055	Code list responsible agency, coded	C an..3	N	Not used
3224	Place/location	C an..17	C an..17	Location city name

Remark:**Example:**

LOC+5+:::ARVIDSJAUR'

LOC+8+DK-5500:::MIDDELFART'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG5	DTM
0260		SG5	C	1	3	TDT-LOC-DTM		
0300	16	DTM	C	9	4	Date/time/period		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
DTM				
C507	DATE/TIME/PERIOD	M	M	
2005	Date/time/period qualifier	M an..3	M an..3	2 Delivery date, requested 64 Delivery time, earliest 63 Delivery time, latest
2380	Date/time/period	C an..35	C an..35	
2379	Date/time/period format qualifier	C an..3	C an..3	102 CCYYMMDD 401 HHMM

Remark:**Example:**

DTM+2:20211022:102'
 DTM+64:1300:401'
 DTM+63:1400:401'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG8	GID
---------	----	-----	----	--------	-------	------	-----	-----

0390		SG8	C	99	3	GID-PCI-SG9-SG10		
Segment group only used for item status								

0400	17	GID	M	1	3	Goods item details		
------	----	------------	---	---	---	---------------------------	--	--

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
GID				
1496	Goods item number	C n..5	C n..5	
C213	NUMBER AND TYPE OF PACKAGES	C	C	
7224	Number of packages	M n..8	M n..8	
7065	Type of packages identification	C an..17	C an..17	

Remark:**Example:**

GID+1+1:CT'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG8	PCI
---------	----	-----	----	--------	-------	------	-----	-----

0390 **SG8** C 99 3 **GID-PCI-SG9-SG10**

Segment group only used for item status

0420 18 **PCI** C 99 4 **Package identification**

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
PCI				
4233	Marking instructions, coded	C an..3	C an..3	24 Shipper assigned
C210	MARKS & LABELS	C	C	
7102	Shipping marks	M an..35	M an..35	Package identification / License plate

Remark:

Example:

PCI+24+373400080151420460 '

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG9	MEA
0430		SG9	C	99	4	MEA		
0440	19	MEA	M	1	4	Measurements		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
MEA				
6311	Measurement application qualifier	M an..3	M an..3	WT Weight VOL Volume
C502	MEASUREMENT DETAILS	C	C	
6313	Measurement dimension, coded	C an..3	C an..3	G Gross weight
C174	VALUE/RANGE	C	C	
6411	Measure unit qualifier	M an..3	M an..3	KGM Kilogram MTQ Cubic metre
6314	Measurement value	C n..18	C n..18	

Remark:

Data from reweigh at DHL. Only sent on agreement.

Example:

MEA+WT+G+KGM:17.4'

MEA+VOL++MTQ:0.213'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG10	DIM
0460		SG10	C	99	4	DIM		
0470	20	DIM	M	1	4	Dimensions		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
DIM				
6145	Dimension qualifier	M an..3	M an..3	1 Gross dimensions
C211	DIMENSIONS	M	M	
6411	Measure unit qualifier	M an..3	M an..3	CMT Centimetre
6168	Length dimension	C n..15	C n..15	
6140	Width dimension	C n..15	C n..15	
6008	Height dimension	C n..15	C n..15	

Remark:

Measurement from reweigh handling at DHL. Only sent on agreement.

Example:

DIM+1+CMT:47:31:36'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	UNT
0490	21	UNT	M	1	0	Message trailer	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
UNT				
0074	Number of segments in a message	M n..6	M n..6	
0062	Message reference number	M an..14	M an..14	

Remark:**Example:**

UNT+16+456 '

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	UNZ
0000	22	UNZ	M	1	0	INTERCHANGE TRAILER	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
UNZ				
0036	Interchange control count	M n..6	M n..6	
0020	Interchange control reference	M an..14	M an..14	

Remark:**Example:**

UNZ+1+123 '

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used



Example Message

No	Tag	Example
01	UNA	UNA:+.? '
02	UNB	UNB+UNOC:3+7330924000002:14+7381000065002:14+120614:0918+123++IFTSTA'
03	UNH	UNH+456+IFTSTA:D:94B:UN:SE0016'
04	BGM	BGM+I77+123456+9'
05	DTM	DTM+137:20211007:102'
	SG1	
06	NAD	NAD+MS+++DHL Freight Sweden'
	SG3	
07	CNI	CNI+1+8005282440'
	SG4	
08	STS	STS+1+24+501'
09	RFF	RFF+CU:16547832'
10	DTM	DTM+7:202110071232:203'
11	FTX	FTX+ACB+++Out for delivery'
12	NAD	NAD+AP+++Erika Svensson'
13	LOC	LOC+14+3710:::Växjö'
	SG5	
14	TDT	TDT+20'
15	LOC	LOC+5+:::ARVIDSJAUR'
16	DTM	DTM+2:20211022:102'
	SG8	
17	GID	GID+1+1:CT'
18	PCI	PCI+24+373400080151420460'
	SG9	
19	MEA	MEA+WT+G+KGM:17.4'
	SG10	
20	DIM	DIM+1+CMT:47:31:36'
21	UNT	UNT+16+456'
22	UNZ	UNZ+1+123'

No = Consecutive segment number

Version history**Version history**

Date/Version	Sg	Segment	Modification/Comment	Updated by
2015-06-01 Version 2.0		BGM	1001 - Code 784 removed.	C Sjölund T Green N Steen
	3	CNI	Data element 1373 removed.	
	9	MEA	Added.	
	10	DIM	Added.	