



Message Implementation Guideline

## DHL FREIGHT (SWEDEN) STATUS MESSAGE

based on

### **IFTSTA**

International multimodal status report message

### **UN D.94B S3**

Version: 2.0

Issue date: 2015-06-01

Author: C Sjölund



Date/Version	Sg	Segment	Modification/Comment	Updated by
2015-06-01 Version 2.0		BGM	1001 - Code 784 removed.	C Sjölund T Green N Steen
	3	CNI	Data element 1373 removed.	
	9	MEA	Added.	
	10	DIM	Added.	

Counter = Counter of segment/group within the standard  
 No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



**Structure / Table of Contents**

Counter	No	Tag	St	MaxOcc	Level	Content	
0000	1	<b>UNA</b>	C	1	0	SERVICE STRING ADVICE	<b>UNA</b>
0000	2	<b>UNB</b>	M	1	0	INTERCHANGE HEADER	<b>UNB</b>
0010	3	<b>UNH</b>	M	1	0	Message header	<b>UNH</b>
0020	4	<b>BGM</b>	M	1	0	Beginning of message	<b>BGM</b>
0030	5	<b>DTM</b>	C	1	1	Date/time/period	<b>DTM</b>
0050		<b>SG1</b>	M	1	1	NAD	<b>SG1</b>
0060	6	<b>NAD</b>	M	1	1	Name and address	<b>NAD</b>
0140		<b>SG3</b>	C	999	1	CNI-SG4	<b>SG3</b>
0150	7	<b>CNI</b>	M	1	1	Consignment information	<b>CNI</b>
0180		<b>SG4</b>	M	99	2	STS-RFF-DTM-FTX-NAD-LOC-SG5-SG8	<b>SG4</b>
0190	8	<b>STS</b>	M	1	2	Status	<b>STS</b>
0200	9	<b>RFF</b>	C	9	3	Reference	<b>RFF</b>
0210	10	<b>DTM</b>	C	1	3	Date/time/period	<b>DTM</b>
0220	11	<b>FTX</b>	C	1	3	Free text	<b>FTX</b>
0230	12	<b>NAD</b>	C	9	3	Name and address	<b>NAD</b>
0240	13	<b>LOC</b>	C	1	3	Place/location identification	<b>LOC</b>
0260		<b>SG5</b>	C	1	3	TDT-LOC	<b>SG5</b>
0270	14	<b>TDT</b>	M	1	3	Details of transport	<b>TDT</b>
0290	15	<b>LOC</b>	C	2	4	Place/location identification	<b>LOC</b>
0390		<b>SG8</b>	C	99	3	GID-PCI-SG9-SG10	<b>SG8</b>
0400	16	<b>GID</b>	M	1	3	Goods item details	<b>GID</b>
0420	17	<b>PCI</b>	C	99	4	Package identification	<b>PCI</b>
0430		<b>SG9</b>	C	99	4	MEA	<b>SG9</b>
0440	18	<b>MEA</b>	M	1	4	Measurements	<b>MEA</b>
0460		<b>SG10</b>	C	99	4	DIM	<b>SG10</b>
0470	19	<b>DIM</b>	M	1	4	Dimensions	<b>DIM</b>
0490	20	<b>UNT</b>	M	1	0	Message trailer	<b>UNT</b>
0000	21	<b>UNZ</b>	M	1	0	INTERCHANGE TRAILER	<b>UNZ</b>

Counter = Counter of segment/group within the standard  
 No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent, A=Advised, N=Not used





Counter	No	Tag	St	MaxOcc	Level	Name	UNB
---------	----	-----	----	--------	-------	------	-----

0000 2 **UNB** M 1 0 INTERCHANGE HEADER

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
UNB				
S001	SYNTAX IDENTIFIER	M	M	
0001	Syntax identifier	M a4	M a4	<b>UNOC UN/ECE level C</b>
0002	Syntax version number	M n1	M n1	<b>3 Syntax version number 3</b>
S002	INTERCHANGE SENDER	M	M	
0004	Sender identification	M an..35	M an..35	
0007	Partner identification code qualifier	C an..4	C an..4	<b>14 EAN (European Article Numbering Association)</b> <b>30 ISO 6523: Organization identification</b>
S003	INTERCHANGE RECIPIENT	M	M	
0010	Recipient identification	M an..35	M an..35	
0007	Partner identification code qualifier	C an..4	C an..4	<b>14 EAN (European Article Numbering Association)</b> <b>30 ISO 6523: Organization identification</b>
S004	DATE/TIME OF PREPARATION	M	M	
0017	Date of preparation	M n6	M n6	
0019	Time of preparation	M n4	M n4	
0020	Interchange control reference	M an..14	M an..14	
S005	RECIPIENT'S REFERENCE PASSWORD	C	N	
0022	Recipient's reference/password	M an..14	N	Not used
0026	Application reference	C an..14	C an..14	Not used for DHL Freight International

**Remark:**

**Example:**

UNB+UNOC:3+733092400002:14+7381000065002:14+120614:0918+123++IFTSTA '

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	UNH
0010	3	<b>UNH</b>	M	1	0	Message header	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
UNH				
0062	Message reference number	M an..14	M an..14	
S009	MESSAGE IDENTIFIER	M	M	
0065	Message type identifier	M an..6	M an..6	<b>IFTSTA International multimodal status report message</b>
0052	Message type version number	M an..3	M an..3	<b>D Draft directory</b>
0054	Message type release number	M an..3	M an..3	<b>94B Version 94B</b>
0051	Controlling agency	M an..2	M an..2	<b>UN UN/ECE/TRADE/WP.4, United Nations Standard Messages (UNSM)</b>
0057	Association assigned code	C an..6	C an..6	<b>SE0016 DHL Freight Domestic DP1.2 DHL Freight International</b>

**Remark:**

**Example:**

UNH+456+IFTSTA:D:94B:UN:SE0016'

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	BGM
0020	4	<b>BGM</b>	M	1	0	Beginning of message	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
BGM				
C002	DOCUMENT/MESSAGE NAME	C	C	
1001	Document/message name, coded	C an..3	C an..3	<b>177 Item/Consignment status</b> <b>77 Consignment status</b>
1004	Document/message number	C an..35	C an..35	Not used for DHL Freight Domestic
1225	Message function, coded	C an..3	C an..3	<b>9 Original</b>

**Remark:**

**Example:**

BGM+I77+123456+9'

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	DTM
---------	----	-----	----	--------	-------	------	-----

0030 5 **DTM** C 1 1 **Date/time/period**

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
DTM				
C507	DATE/TIME/PERIOD	M	M	
2005	Date/time/period qualifier	M an..3	M an..3	<b>137 Document/message date/time</b>
2380	Date/time/period	C an..35	C an..35	
2379	Date/time/period format qualifier	C an..3	C an..3	<b>102 CCYMMDD</b> <b>203 CCYMMDDHHMM</b>

**Remark:**

**Example:**

DTM+137:20141007:102'  
DTM+137:201410071245:203'

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the segment/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used





Counter	No	Tag	St	MaxOcc	Level	Name	SG1	NAD
0050		<b>SG1</b>	M	1	0	<b>NAD</b>		
0060	6	<b>NAD</b>	M	1	1	<b>Name and address</b>		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
NAD				
3035	Party qualifier	M an..3	M an..3	<b>MS Document/message issuer/sender</b>
C082	PARTY IDENTIFICATION DETAILS	C	N	
3039	Party id. identification	M an..35	N	Not used
C058	NAME AND ADDRESS	C	N	
3124	Name and address line	M an..35	N	Not used
C080	PARTY NAME	C	C	
3036	Party name	M an..35	M an..35	DHL Freight Sweden

**Remark:**

**Example:**

NAD+MS+++DHL Freight Sweden'

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG3	CNI
0140		<b>SG3</b>	C	999	1	<b>CNI-SG4</b>		
0150	7	<b>CNI</b>	M	1	1	<b>Consignment information</b>		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
CNI				
1490	Consolidation item number	C n..4	C n..4	
C503	DOCUMENT/MESSAGE DETAILS	C	C	
1004	Document/message number	C an..35	C an..35	DHL Freight Domestic: DHL shipment number DHL Freight International: DHL Order code

**Remark:**

**Example:**

CNI+1+8005282440 '  
CNI+1+HAD-EC-9545754 '

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the segment/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG4	STS
0180		<b>SG4</b>	M	99	2	<b>STS-RFF-DTM-FTX-NAD-LOC-SG5-SG8</b>		
0190	8	<b>STS</b>	M	1	2	<b>Status</b>		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
STS				
C601	STATUS TYPE	C	C	
9015	Status type, coded	M an..3	M an..3	<b>1 Transport</b>
C555	STATUS EVENT	C	C	
9011	Status event, coded	M an..3	M an..3	See separate code list
C556	STATUS REASON	C	C	
9013	Status reason, coded	M an..3	M an..3	See separate code list

**Remark:**

**Example:**

STS+1+20+234'

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG4	RFF
0180		<b>SG4</b>	M	99	2	STS-RFF-DTM-FTX-NAD-LOC-SG5-SG8		
0200	9	<b>RFF</b>	C	9	3	Reference		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
RFF				
C506	REFERENCE	M	M	
1153	Reference qualifier	M an..3	M an..3	<b>AAS Transport document number</b> <b>CU Consignor reference</b> <b>AAO Consignee reference</b> Other references that are used in shipment information are also sent (maximum 9 repetitions).
1154	Reference number	C an..35	C an..35	

**Remark:**

**Example:**

RFF+CU:16547832'

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG4	DTM
0180		<b>SG4</b>	M	99	2	STS-RFF-DTM-FTX-NAD-LOC-SG5-SG8		
0210	10	<b>DTM</b>	C	1	3	Date/time/period		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
DTM				
C507	DATE/TIME/PERIOD	M	M	
2005	Date/time/period qualifier	M an..3	M an..3	<b>7 Effective date/time</b>
2380	Date/time/period	C an..35	C an..35	
2379	Date/time/period format qualifier	C an..3	C an..3	<b>203 CCYMMDDHHMM</b>

**Remark:**

**Example:**

DTM+7:201410071232:203'

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG4	FTX
0180		<b>SG4</b>	M	99	2	<b>STS-RFF-DTM-FTX-NAD-LOC-SG5-SG8</b>		
0220	11	<b>FTX</b>	C	1	3	<b>Free text</b>		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
FTX				
4451	Text subject qualifier	M an..3	M an..3	<b>ACB Additional information</b> <b>AAI Remark</b> <b>PRD Product information</b>
4453	Text function, coded	C an..3	N	Not used
C107	TEXT REFERENCE	C	C	
4441	Free text, coded	M an..3	M an..3	Used with qualifier PRD: Product code
C108	TEXT LITERAL	C	C	
4440	Free text	M an..70	M an..70	Used with qualifier ACB: Status description Used with qualifier AAI: Remark Used with qualifier PRD: Product name

**Remark:**

**Example:**

FTX+ACB+++Out for delivery'  
 FTX+AAI+++Agreed delivery date 22.6.2012.'  
 FTX+PRD++102+DHL PAKET'

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG4	NAD
0180		<b>SG4</b>	M	99	2	<b>STS-RFF-DTM-FTX-NAD-LOC-SG5-SG8</b>		
0230	12	<b>NAD</b>	C	9	3	<b>Name and address</b>		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
NAD				
3035	Party qualifier	M an..3	M an..3	<b>AP Accepting party</b> <b>FP Freight/charges payer</b> <b>CZ Consignor</b> For DHL Freight International import shipments CZ equals the Consignee, i.e. the Swedish customer.
C082	PARTY IDENTIFICATION DETAILS	C	C	
3039	Party id. identification	M an..35	M an..35	Used with qualifier CZ: Consignor DHL account number
C058	NAME AND ADDRESS	C	N	
3124	Name and address line	M an..35	N	Not used
C080	PARTY NAME	C	C	
3036	Party name	M an..35	M an..35	Used with qualifier AP: Accepting party (IOD name)

**Remark:**

**Example:**

NAD+AP+++Erika Svensson'  
NAD+CZ+405555'

No = Consecutive segment number  
MaxOcc = Maximum occurrence of the segment/group  
Counter = Counter of segment/group within the standard

St = Status  
EDIFACT: M=Mandatory, C=Conditional  
User specific: R=Required, O=Optional, D=Dependent,  
A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG4	LOC
0180		<b>SG4</b>	M	99	2	STS-RFF-DTM-FTX-NAD-LOC-SG5-SG8		
0240	13	<b>LOC</b>	C	1	3	Place/location identification		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
LOC				
3227	Place/location qualifier	M an..3	M an..3	<b>14 Event location</b>
C517	LOCATION IDENTIFICATION	C	C	
3225	Place/location identification	C an..25	C an..25	For DHL Freight Domestic: DHL Terminal code For DHL Freight International: DHL Terminal name
1131	Code list qualifier	C an..3	N	Not used
3055	Code list responsible agency, coded	C an..3	N	Not used
3224	Place/location	C an..17	C an..17	Event location city name

**Remark:**

**Example:**

LOC+14+3710:::Växjö'  
 LOC+14+Hamburg:::Hamburg'

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used





Counter	No	Tag	St	MaxOcc	Level	Name	SG5	TDT
0260		<b>SG5</b>	C	1	3	TDT-LOC		
0270	14	<b>TDT</b>	M	1	3	Details of transport		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
TDT				
8051	Transport stage qualifier	M an..3	M an..3	<b>20 Main-carriage transport</b>

**Remark:**

**Example:**

TDT+20'

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG5	LOC
0260		<b>SG5</b>	C	1	3	TDT-LOC		
0290	15	<b>LOC</b>	C	2	4	Place/location identification		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
LOC				
3227	Place/location qualifier	M an..3	M an..3	<b>5 Place of departure</b> <b>8 Place of destination</b>
C517	LOCATION IDENTIFICATION	C	C	
3225	Place/location identification	C an..25	C an..25	Postal code (including country code) Not used for DHL Freight Domestic
1131	Code list qualifier	C an..3	N	Not used
3055	Code list responsible agency, coded	C an..3	N	Not used
3224	Place/location	C an..17	C an..17	Location city name

**Remark:**

**Example:**

LOC+5+:::ARVIDSJAUR '  
 LOC+8+DK-5500:::MIDDELFART '

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG8	GID
0390		<b>SG8</b>	C	99	3	<b>GID-PCI-SG9-SG10</b>		
Segment group only used for item status								
0400	16	<b>GID</b>	M	1	3	<b>Goods item details</b>		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
GID				
1496	Goods item number	C n..5	C n..5	
C213	NUMBER AND TYPE OF PACKAGES	C	C	
7224	Number of packages	M n..8	M n..8	
7065	Type of packages identification	C an..17	C an..17	

**Remark:**

**Example:**

GID+1+1:CT'

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG8	PCI
0390		<b>SG8</b>	C	99	3	<b>GID-PCI-SG9-SG10</b>		
Segment group only used for item status								
0420	17	<b>PCI</b>	C	99	4	<b>Package identification</b>		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
PCI				
4233	Marking instructions, coded	C an..3	C an..3	<b>24 Shipper assigned</b>
C210	MARKS & LABELS	C	C	
7102	Shipping marks	M an..35	M an..35	Package identification / License plate

**Remark:**

**Example:**

PCI+24+373400080151420460'

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG9	MEA
0430		<b>SG9</b>	C	99	4	MEA		
0440	18	<b>MEA</b>	M	1	4	Measurements		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
MEA				
6311	Measurement application qualifier	M an..3	M an..3	<b>WT Weight</b> <b>VOL Volume</b>
C502	MEASUREMENT DETAILS	C	C	
6313	Measurement dimension, coded	C an..3	C an..3	<b>G Gross weight</b>
C174	VALUE/RANGE	C	C	
6411	Measure unit qualifier	M an..3	M an..3	<b>KGM Kilogram</b> <b>MTQ Cubic metre</b>
6314	Measurement value	C n..18	C n..18	

**Remark:**

Data from reweigh at DHL. Only sent on agreement.

**Example:**

MEA+WT+G+KGM:17.4'

MEA+VOL++MTQ:0.213'

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	SG10	DIM
0460		<b>SG10</b>	C	99	4	<b>DIM</b>		
0470	19	<b>DIM</b>	M	1	4	<b>Dimensions</b>		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
DIM				
6145	Dimension qualifier	M an..3	M an..3	<b>1 Gross dimensions</b>
C211	DIMENSIONS	M	M	
6411	Measure unit qualifier	M an..3	M an..3	<b>CMT Centimetre</b>
6168	Length dimension	C n..15	C n..15	
6140	Width dimension	C n..15	C n..15	
6008	Height dimension	C n..15	C n..15	

**Remark:**

Measurement from reweigh handling at DHL. Only sent on agreement.

**Example:**

DIM+1+CMT:47:31:36'

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	UNT
0490	20	<b>UNT</b>	M	1	0	Message trailer	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
UNT				
0074	Number of segments in a message	M n..6	M n..6	
0062	Message reference number	M an..14	M an..14	

**Remark:**

**Example:**

UNT+16+456'

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used



Counter	No	Tag	St	MaxOcc	Level	Name	UNZ
0000	21	<b>UNZ</b>	M	1	0	INTERCHANGE TRAILER	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
UNZ				
0036	Interchange control count	M n..6	M n..6	
0020	Interchange control reference	M an..14	M an..14	

**Remark:**

**Example:**

UNZ+1+123'

No = Consecutive segment number  
 MaxOcc = Maximum occurrence of the segment/group  
 Counter = Counter of segment/group within the standard

St = Status  
 EDIFACT: M=Mandatory, C=Conditional  
 User specific: R=Required, O=Optional, D=Dependent,  
 A=Advised, N=Not used





**Example Message**

No	Tag	Example
01	<b>UNA</b>	UNA:+.? '
02	<b>UNB</b>	UNB+UNOC:3+7330924000002:14+7381000065002:14+120614:0918+123++IFTSTA'
03	<b>UNH</b>	UNH+456+IFTSTA:D:94B:UN:SE0016'
04	<b>BGM</b>	BGM+I77+123456+9'
05	<b>DTM</b>	DTM+137:20141007:102'
<b>SG1</b>		
06	<b>NAD</b>	NAD+MS+++DHL Freight Sweden'
<b>SG3</b>		
07	<b>CNI</b>	CNI+1+8005282440'
<b>SG4</b>		
08	<b>STS</b>	STS+1+20+234'
09	<b>RFF</b>	RFF+CU:16547832'
10	<b>DTM</b>	DTM+7:201410071232:203'
11	<b>FTX</b>	FTX+ACB+++Out for delivery'
12	<b>NAD</b>	NAD+AP+++Erika Svensson'
13	<b>LOC</b>	LOC+14+3710:::Växjö'
<b>SG5</b>		
14	<b>TDT</b>	TDT+20'
15	<b>LOC</b>	LOC+5+:::ARVIDSJAUR'
<b>SG8</b>		
16	<b>GID</b>	GID+1+1:CT'
17	<b>PCI</b>	PCI+24+373400080151420460'
<b>SG9</b>		
18	<b>MEA</b>	MEA+WT+G+KGM:17.4'
<b>SG10</b>		
19	<b>DIM</b>	DIM+1+CMT:47:31:36'
20	<b>UNT</b>	UNT+16+456'
21	<b>UNZ</b>	UNZ+1+123'

No = Consecutive segment number