



Message Implementation Guideline

DHL SERVICE POINT SHIPMENT INSTRUCTION

based on

IFTMIN

Instruction message

UN S.93A S3

Version: 2.8

Issue date: 2014-12-09

Author: CHRISTER SJÖLUND

Version history

Date/Version	Sg	Segment	Modification/Comment	Updated by
2011-02-01 Version 2.3			This specification is valid from 2011-03-01.	C Sjölund
		UNH	0068 (Name and version of software or application) required for customer applications.	
		TSR	4065 New product codes added. 103 = DHL SERVICE POINT B2C 104 = DHL SERVICE POINT C2B	
		TSR	7273 Removed.	
	3	RFF	1153 AAO added. Consignee's reference number. SS added. Used for C.O.D reference.	
	10	NAD	3036-2 Removed. SERVICE POINT ID (in format SE-123400) no longer needed.	
	19	MEA	6311 Code VOL added for volume. 6411 Code MTQ added for cubic metre.	
2011-04-20 Version 2.4		MOA	5025 Updated with code 157 for Insurance amount.	C Sjölund
		MOA	Example updated with amount including decimals.	
		FTX	4441 Updated with code 01 for Insurance.	
	14	RFF	1153 Codes Z01 and Z04 added for Bank giro- and Plus giro number. 1154 Added. Giro number.	
			Example 3.3.2 updated with C.O.D amount including decimals and bank giro number.	
			Example 3.4 updated with MOA and FTX including Insurance info.	
2011-08-18 Version 2.5		FTX	4441 Added two codes for additional services CO2 Klimatkompensation and Begränsad mängd farligt gods.	C Sjölund
	6	CPI	4237 Added code 4 for third party as possible freight payer for B2C.	
	10	NAD	3035 Added qualifier FP for third party payer. 3039 Third party DHL account number to be sent here.	

Counter = Counter of segment/group within the standard
 No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Date/Version	Sg	Segment	Modification/Comment	Updated by
2011-09-05 Version 2.5		FTX	Changed name on additional service from CO2 Klimatkompensation to Miljöfrakt.	C Sjölund
		FTX	4440 Maximum length for e-mail address is 64 characters.	
2012-03-06 Version 2.6		MOA	Max number of repetitions changed to 2.	C Sjölund
		FTX	4441 - Code 32 added for additional service Påminnelse via brevavisering. 4441 - Codes 70, 72, 74, 78, 82 and 84 added for additional service Leveransbevakning. 4440-1 and 4440-2 used for mail address and/or sms phone number for additional service Leveransbevakning.	
2012-10-15 Version 2.7		FTX	4441 - Code 32 for additional service Påminnelse via brevavisering removed.	C Sjölund
	10	NAD	Party PW can be used for product B2C and party DP can be used for product C2B.	
2014-12-09 Version 2.8		FTX	4441 - Codes 581, 582, 584 and 586 added for e-mail address to parties.	C Sjölund

Counter = Counter of segment/group within the standard
 No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Structure / Table of Contents

Counter	No	Tag	St	MaxOcc	Level	Content	
0000	1	UNA	C	1	0	SERVICE STRING ADVICE	UNA
0000	2	UNB	M	1	0	INTERCHANGE HEADER	UNB
0010	3	UNH	M	1	0	MESSAGE HEADER	UNH
0020	4	BGM	M	1	0	BEGINNING OF MESSAGE	BGM
0050	5	DTM	C	2	1	DATE/TIME/PERIOD	DTM
0060	6	TSR	R	1	1	TRANSPORT SERVICE REQUIREMENTS	TSR
0080	7	MOA	C	2	1	MONETARY AMOUNT	MOA
0090	8	FTX	C	9	1	FREE TEXT	FTX
0100	9	CNT	C	5	1	CONTROL TOTAL	CNT
0170		SG3	C	99	1	RFF-DTM	SG3
0180	10	RFF	M	1	1	REFERENCE	RFF
0250		SG6	C	1	1	CPI	SG6
0260	11	CPI	M	1	1	CHARGE PAYMENT INSTRUCTIONS	CPI
0400		SG8	M	3	1	TDT	SG8
0410	12	TDT	M	1	1	DETAILS OF TRANSPORT	TDT
0480		SG10	M	6	1	NAD-SG11-SG14	SG10
0490	13	NAD	M	1	1	NAME AND ADDRESS	NAD
0520		SG11	C	2	2	CTA-COM	SG11
0530	14	CTA	M	1	2	CONTACT INFORMATION	CTA
0540	15	COM	C	9	3	COMMUNICATION CONTACT	COM
0650		SG14	C	9	2	RFF	SG14
0660	16	RFF	M	1	2	REFERENCE	RFF
0730		SG16	C	999	1	GID-SG19	SG16
0740	17	GID	M	1	1	GOODS ITEM DETAILS	GID
0890		SG19	C	4	2	MEA	SG19
0900	18	MEA	M	1	2	MEASUREMENTS	MEA
1590	19	UNT	M	1	0	MESSAGE TRAILER	UNT
0000	20	UNZ	M	1	0	INTERCHANGE TRAILER	UNZ

Counter = Counter of segment/group within the standard
 No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	UNB
--------	----	-----	----	--------	-------	------	-----

0000 2 **UNB** M 1 0 INTERCHANGE HEADER

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
UNB				
S001	SYNTAX IDENTIFIER	M	M	
0001	Syntax identifier	M a4	M a4	UNOC
0002	Syntax version number	M n1	M n1	3
S002	INTERCHANGE SENDER	M	M	
0004	Sender identification	M an..35	M an..35	ID filesender
0007	Partner identification code qualifier	C an..4	C an..4	14 EAN (International Article Numbering Association) 30 ISO 6523: Organization identification
S003	INTERCHANGE RECIPIENT	M	M	
0010	Recipient identification	M an..35	M an..35	DHL EAN address
0007	Partner identification code qualifier	C an..4	C an..4	14 EAN (International Article Numbering Association)
S004	DATE/TIME OF PREPARATION	M	M	
0017	Date of preparation	M n6	M n6	
0019	Time of preparation	M n4	M n4	
0020	Interchange control reference	M an..14	M an..14	Unique reference for the interchange

Remark:

Example:

UNB+UNOC: 3+UNIQUE_SENDER_ID: 30+7330924000002:14+110201:1549+456'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	UNH
0010	3	UNH	M	1	0	MESSAGE HEADER	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
UNH				
0062	Message reference number	M an..14	M an..14	Unique reference for the message.
S009	MESSAGE IDENTIFIER	M	M	
0065	Message type identifier	M an..6	M an..6	IFTMIN
0052	Message type version number	M an..3	M an..3	S
0054	Message type release number	M an..3	M an..3	93A
0051	Controlling agency	M an..2	M an..2	UN
0057	Association assigned code	C an..6	R an..6	SE0020
0068	Common access reference	C an..35	C an..35	Name and version of software or application.

Remark:

0068 required for customer applications.

Example:

UNH+5150+IFTMIN:S:93A:UN:SE0020+MyCustomerApplication v4.7'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	BGM
0020	4	BGM	M	1	0	BEGINNING OF MESSAGE	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
BGM				
C002	DOCUMENT/MESSAGE NAME	C	R	
1001	Document/message name, coded	C an..3	R an..3	700 Shipment instruction
1004	Document/message number	C an..35	C an..35	
1225	Message function, coded	C an..3	C an..3	9 Original

Remark:

Example:

BGM+700+5252725018+9'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	DTM
0050	5	DTM	C	2	1	DATE/TIME/PERIOD	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
DTM				
C507	DATE/TIME/PERIOD	M	M	
2005	Date/time/period qualifier	M an..3	M an..3	137 Document/message date/time
2380	Date/time/period	C an..35	R an..35	
2379	Date/time/period format qualifier	C an..3	R an..3	101 YYMMDD 102 CCYYMMDD

Remark:

Example:

DTM+137:20110502:102'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	TSR
--------	----	-----	----	--------	-------	------	-----

0060 6 **TSR** R 1 1 **TRANSPORT SERVICE REQUIREMENTS**

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
TSR				
C536	CONTRACT AND CARRIAGE CONDITION	C	R	
4065	Contract and carriage condition, coded	M an..3	M an..3	Used for product code. 103 DHL SERVICE POINT B2C 104 DHL SERVICE POINT C2B

Remark:

Example:
TSR+103'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	MOA
0080	7	MOA	C	2	1	MONETARY AMOUNT	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
MOA				
C516	MONETARY AMOUNT	M	M	
5025	Monetary amount type qualifier	M an..3	M an..3	22 Cash on delivery amount 157 Insurance amount
5004	Monetary amount	C n..18	R n..18	
6345	Currency, coded	C an..3	C an..3	SEK default value for Domestic products.

Remark:

Example:

MOA+22:3850.00:SEK'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	FTX
0090	8	FTX	C	9	1	FREE TEXT	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
FTX				
4451	Text subject qualifier	M an..3	M an..3	<p>ARR Arrival conditions</p> <p>ARR is used for: E-mail address to be notified (B2C shipments) with: - e-mail address in 4440-1</p> <p>Additional service Leveransbevakning (B2C shipments) with: - code for event in 4441 - e-mail address and/or sms phone number in 4440-1 and 4440-2</p> <p>E-mail address to parties with: - code for party in 4441 - e-mail address in 4440-1</p> <p>DIN Delivery instructions</p> <p>DIN is used for other additional services</p>
4453	Text function, coded	C an..3	N	Not used
C107	TEXT REFERENCE	C	C	
4441	Free text, coded	M an..3	M an..3	<p>Used for additional services with qualifier DIN in 4451:</p> <p>01 Försäkring / Insurance 02 Miljöfrakt / CO2 Climate compensation 09 Begränsad mängd farligt gods / Limited quantity dangerous goods 13 Efterkrav / Cash on delivery (C.O.D)</p> <p>Used for additional service Leveransbevakning with qualifier ARR in 4451 and e-mail address and/or sms phone number in 4440-1 and 4440-2: (Notice that 4440-1 must always be used if only one of e-mail address or phone number is sent.)</p> <p>70 Leveransbevakning via e-post/sms - Scan event Pickup 72 Leveransbevakning via e-post/sms - Scan event Arrived to DHL terminal 74 Leveransbevakning via e-post/sms - Scan event Out for delivery 78 Leveransbevakning via e-post/sms - Scan event Delivered 82 Leveransbevakning via e-post/sms - Scan event Collected by receiver 84 Leveransbevakning via e-post/sms - Scan event Not collected by receiver</p> <p>Used for e-mail address to parties with qualifier ARR in 4451 and e-mail address in 4440-1: 581 Despatch party e-mail address (B2C) 582 Consignor e-mail address (B2C) 584 Consignee e-mail address (C2B)</p>

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent, A=Advised, N=Not used



Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
586 Delivery party e-mail address (C2B)				
C108	TEXT LITERAL	C	C	
4440	Free text	M an..70	M an..70	Maximum length for e-mail address is 64 characters.
4440	Free text	C an..70	C an..70	

Remark:

Example:

FTX+DIN++13'
 Additional service Efterkrav.

FTX+ARR+++ellen.persson@xmail.com'
 Mail address to be notified (if notification via e-mail is selected).

FTX+ARR++70+0706322106'
 FTX+ARR++82+christer.sjolund@dhl.com:0706012236'
 Shipment with Leveransbevakning for events Pickup and Collected by receiver including sms phone number for the first event and e-mail address + sms phone number for the second event.

FTX+ARR++582+mail@consignor.se'
 E-mail address to consignor (B2C shipment).

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	CNT
0100	9	CNT	C	5	1	CONTROL TOTAL	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
CNT				
C270	CONTROL	M	M	
6069	Control qualifier	M an..3	M an..3	7 Total gross weight 11 Total number of packages 15 Total consignment, cube
6066	Control value	M n..18	M n..18	
6411	Measure unit qualifier	C an..3	R an..3	KGM Kilogram * PCE Piece MTQ Cubic metre *

Remark:

Example:

CNT+7:4:KGM'
 CNT+11:1:PCE'
 CNT+15:0.045:MTQ'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	SG3	RFF
0170		SG3	C	99	1	RFF-DTM		
0180	10	RFF	M	1	1	REFERENCE		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
RFF				
C506	REFERENCE	M	M	
1153	Reference qualifier	M an..3	M an..3	<p>AAS Transport document number AAS is used for shipment number and is mandatory.</p> <p>CU Consignor's reference number CU can only be used for B2C shipments.</p> <p>SS Sellers reference number SS is used for C.O.D reference.</p> <p>AAO Consignee's shipment reference number AAO can only be used for C2B shipments.</p>
1154	Reference number	C an..35	R an..35	

Remark:

Example:

RFF+AAS:6905280324'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	SG6	CPI
0250		SG6	C	1	1	CPI		
0260	11	CPI	M	1	1	CHARGE PAYMENT INSTRUCTIONS		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
CPI				
C229	CHARGE CATEGORY	C	N	
5237	Charge category, coded	M an..3	N	Not used
C231	METHOD OF PAYMENT	C	N	
4215	Transport charges method of payment, coded	M an..3	N	Not used
4237	Prepaid/collect indicator, coded	C an..3	R an..3	<p>1 Consignor (Sender) pays (Consignor DHL account number in NAD+CZ 3039)</p> <p>4 Third party pays (Payer DHL account number in NAD+FP 3039)</p> <p>1 or 4 is mandatory for B2C.</p> <p>3 Consignee (Receiver) pays (Consignee DHL account number in NAD+CN 3039)</p> <p>3 is mandatory for C2B.</p>

Remark:

Example:

CPI+++1'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	SG8	TDT
0400		SG8	M	3	1	TDT		
0410	12	TDT	M	1	1	DETAILS OF TRANSPORT		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
TDT				
8051	Transport stage qualifier	M an..3	M an..3	20 Main-carriage transport

Remark:

Example:

TDT+20'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	SG10	NAD
0480		SG10	M	6	1	NAD-SG11-SG14		
0490	13	NAD	M	1	1	NAME AND ADDRESS		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
NAD				
3035	Party qualifier	M an..3	M an..3	<p>CZ Consignor PW Despatch party PW can only be used for product B2C.</p> <p>CN Consignee ST Ship to ST is used for receiving SERVICE POINT terminal ID (like 6514) in 3039.</p> <p>DP Delivery party For product B2C, DP is used for receiving SERVICE POINT name and address information. For product C2B, DP can be used for Delivery party (if other than Consignee).</p> <p>FP Freight/charges payer FP is used for third party DHL account number when CPI 4237=4.</p>
C082	PARTY IDENTIFICATION DETAILS	C	C	
3039	Party id identification	M an..17	M an..17	<p>Consignor DHL account number in NAD+CZ mandatory for B2C.</p> <p>Receiving SERVICE POINT Terminal Id in NAD+ST mandatory for B2C. Notice that only the four digit Id should be used here. For example if the Id from the Locator response is SE-651400, the Id in NAD 3039 should be 6514.</p> <p>Consignee DHL account number in NAD+CN mandatory for C2B.</p> <p>Freight payer DHL account number in NAD+FP when CPI 4237=4.</p>
C058	NAME AND ADDRESS	C	N	
3124	Name and address line	M an..35	N	Not used
C080	PARTY NAME	C	C	
3036	Party name	M an..35	M an..35	
C059	STREET	C	C	
3042	Street and number/P.O. Box	M an..35	M an..35	Delivery address
3042	Street and number/P.O. Box	C an..35	C an..35	Additional address
3164	City name	C an..35	C an..35	
3229	Country sub-entity identification	C an..9	N	Not used
3251	Postcode identification	C an..9	C an..9	Postal code
3207	Country, coded	C an..3	C an..3	

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent, A=Advised, N=Not used



Remark:

Example:

NAD+CZ+123456++Webbutiken AB+Tallstigen 12:Additional address+Stockholm++10528+SE'

NAD+CN+++Ellen Persson+Åkergatan 22+Kumla++69211+SE'

NAD+ST+6514'

NAD+DP+++Interflora+Byvägen 6+Kumla++69218+SE'

NAD+FP+112233'

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	SG11	CTA
0520		SG11	C	2	2	CTA-COM		
0530	14	CTA	M	1	2	CONTACT INFORMATION		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
CTA				
3139	Contact function, coded	C an..3	R an..3	<p>NT Notification contact NT is used in NAD+CN when sms notification is wanted. (Mobile phone number in COM 3148.)</p> <p>IC Information contact If CTA+NT (sms notification) is used, CTA+IC should not be used in NAD+CN.</p> <p>CTA should only be used once per NAD.</p>

Remark:

Example:

CTA+NT '

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	SG11	COM
0520		SG11	C	2	2	CTA-COM		
0540	15	COM	C	9	3	COMMUNICATION CONTACT		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
COM				
C076	COMMUNICATION CONTACT	M	M	
3148	Communication number	M an..25	M an..25	
3155	Communication channel qualifier	M an..3	M an..3	TE Telephone

Remark:

Example:

COM+0705429188:TE'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	SG14	RFF
0650		SG14	C	9	2	RFF		
0660	16	RFF	M	1	2	REFERENCE		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
RFF				
C506	REFERENCE	M	M	
1153	Reference qualifier	M an..3	M an..3	Z01 Bank giro number
1154	Reference number	C an..35	C an..35	Z04 Plus giro number

Remark:

Example:

RFF+Z01:7320427'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	SG16	GID
0730		SG16	C	999	1	GID-SG19		
0740	17	GID	M	1	1	GOODS ITEM DETAILS		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
GID				
1496	Goods item number	C n..5	C n..5	Counter
C213	NUMBER AND TYPE OF PACKAGES	C	C	
7224	Number of packages	M n..8	M n..8	Always value 1 for DHL SERVICE POINT shipments.

Remark:

Example:
GID+1+1'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	SG19	MEA
0890		SG19	C	4	2	MEA		
0900	18	MEA	M	1	2	MEASUREMENTS		

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
MEA				
6311	Measurement application qualifier	M an..3	R an..3	WT Weights VOL Volume
C502	MEASUREMENT DETAILS	C	C	C502 required for MEA with WT (weight).
6313	Measurement dimension, coded	C an..3	C an..3	G Gross weight
C174	VALUE/RANGE	C	C	
6411	Measure unit qualifier	M an..3	R an..3	KGM Kilogram * MTQ Cubic metre *
6314	Measurement value	C n..18	R n..18	

Remark:

Example:

MEA+WT+G+KGM: 4 '
MEA+VOL++MTQ: 0.195 '

No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group
Counter = Counter of segment/group within the standard

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	UNT
1590	19	UNT	M	1	0	MESSAGE TRAILER	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
UNT				
0074	Number of segments in a message	M n..6	M n..6	
0062	Message reference number	M an..14	M an..14	

Remark:

Example:

UNT+16+5150'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Counte	No	Tag	St	MaxOcc	Level	Name	UNZ
0000	20	UNZ	M	1	0	INTERCHANGE TRAILER	

Standard			Implementation	
Tag	Name	St Format	St Format	Usage / Remark
UNZ				
0036	Interchange control count	M n..6	M n..6	
0020	Interchange control reference	M an..14	M an..14	

Remark:

Example:

UNZ+1+456'

No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group
 Counter = Counter of segment/group within the standard

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



Example Messages

Example 3.3.1 B2C shipment information (with notification via email)

UNA:+.? '
 UNB+UNOC:3+UNIQUE_SENDER_ID:30+7330924000002:14+110201:1507+123'
 UNH+1+IFTMIN:S:93A:UN:SE0020+MyCustomerApplication v4.7'
 BGM+700+5252725018+9'
 DTM+137:20110201:102'
 TSR+103'
 FTX+ARR+++ellen.persson@xmail.com'
 CNT+7:3:KGM'
 CNT+11:1:PCE'
 CNT+15:0.045:MTQ'
 RFF+AAS:5252725018'
 RFF+CU:REF 12345'
 CPI+++1'
 TDT+20'
 NAD+CZ+123456++Postorderkompaniet+Postvägen 1+Örebro++70212+SE'
 NAD+CN+++Ellen Persson+Åkergatan 22+Kumla++69211+SE'
 NAD+ST+6514'
 NAD+DP+++Interflora+Byvägen 6+Kumla++69218+SE'
 GID+1+1'
 MEA+WT+G+KGM:3'
 MEA+VOL++MTQ:0.045'
 UNT+20+1'
 UNZ+1+123'

Counter = Counter of segment/group within the standard
 No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used



**Example 3.3.2 B2C shipment information (with notification via sms)
including additional service Efterkrav (C.O.D)**

UNA:+.? '
 UNB+UNOC:3+UNIQUE_SENDER_ID:30+7330924000002:14+110201:1507+456'
 UNH+1+IFTMIN:S:93A:UN:SE0020+MyCustomerApplication v4.7'
 BGM+700+5252725018+9'
 DTM+137:20110502:102'
 TSR+103'
 MOA+22:3850.00:SEK'
 FTX+DIN++13'
 CNT+7:2:KGM'
 CNT+11:1:PCE'
 RFF+AAS:5252725018'
 RFF+SS:Efterkravsreferens'
 CPI+++1'
 TDT+20'
 NAD+CZ+123456++Postorderkompaniet+Postvägen 1+Örebro++70212+SE'
 RFF+Z01:7320427'
 NAD+CN+++Ellen Persson+Åkergatan 22+Kumla++69211+SE'
 CTA+NT'
 COM+0705429188:TE'
 NAD+ST+6514'
 NAD+DP+++Interflora+Byvägen 6+Kumla++69218+SE'
 GID+1+1'
 MEA+WT+G+KGM:3'
 UNT+22+1'
 UNZ+1+456'

Counter = Counter of segment/group within the standard
 No = Consecutive segment number
 MaxOcc = Maximum occurrence of the segment/group

St = Status
 EDIFACT: M=Mandatory, C=Conditional
 User specific: R=Required, O=Optional, D=Dependent,
 A=Advised, N=Not used

**Example 3.4 C2B return shipment information including additional service Insurance**

UNA:+.? '
UNB+UNOC:3+UNIQUE_SENDER_ID:30+DPST+110301:1507+789'
UNH+1+IFTMIN:S:93A:UN:SE0020+MyCustomerApplication v4.7'
BGM+700+5252725025+9'
DTM+137:20110502:102'
TSR+104'
MOA+157:735.00:SEK'
FTX+DIN++01'
CNT+7:5.5:KGM'
CNT+11:1:PCE'
RFF+AAS:5252725025'
RFF+AAO:MottagarensRef'
CPI+++3'
TDT+20'
NAD+CZ+++Ellen Persson+Åkergatan 22+Kumla++69211+SE'
NAD+CN+123456++Postorderkompaniet+Postvägen 1+Örebro++70212+SE'
GID+1+1'
MEA+WT+G+KGM:3'
UNT+17+1'
UNZ+1+789'

Counter = Counter of segment/group within the standard
No = Consecutive segment number
MaxOcc = Maximum occurrence of the segment/group

St = Status
EDIFACT: M=Mandatory, C=Conditional
User specific: R=Required, O=Optional, D=Dependent,
A=Advised, N=Not used